

Windows installer for Stubby

- [Overview](#)
- [Installation](#)
 - [Release notes](#)
 - [Version 0.2.6](#)
 - [Version 0.2.5](#)
- [Configuration](#)
- [Run Stubby](#)
- [Test Stubby](#)
- [Modify your upstream resolvers](#)
 - [Modify your upstream resolvers \(Windows 7\)](#)
- [Create a Scheduled Task](#)
- [Known Issues](#)
- [Manual update of system resolvers on Windows](#)
 - [Opportunistic mode](#)

Overview

Stubby can be installed

- either via the install/zip packages available on this page or
- by using chocolatey: <https://chocolatey.org/packages/stubby/0.2.6.0>

In both cases a command line interface for Stubby. A future release will include a Graphical Interface to manage Stubby.



Stubby has been tested on Windows 10, should work on Windows 8. There is limited support for Windows 7 - see below.

User testing reports, bug reports and patches/pull requests are all welcomed via [the Stubby github issue tracker!](#)

Installation



The installer currently overwrites all existing files so if you have made changes to the `stubby.yml` then you should create a backup of this file before upgrading!

Release notes

Version 0.2.6

- Update to use Stubby 0.2.6

Version 0.2.5

- Previous versions of the installer were numbered 0.0.1 to 0.0.7. From this release onward we are adopting a new policy. Installer releases will have a 4 component version a.b.c.d. a.b.c gives the Stubby version. d indicates the installer package revision, starting at 0 for the first packaging of a given Stubby version.
- The 0.2.5.0 release now provides a 32bit install as well as a 64bit install.
 - On a 64bit Windows installation, a 32bit install will place files in `C:\Program Files (x86)\Stubby`. All other installs place files in `C:\Program Files\Stubby`.
- This release corrects the default configuration file location to `C:\Program Files\Stubby\stubby.yml`. This path no longer needs to be specified on the command line.
- `stubby.bat` has been updated to look for the configuration file in the same directory as the Stubby executable.

Latest installer is version 0.2.6.0 built from:


- getdns version: 1.5.2
- openssl version: 1.1.1b
- stubby version: 0.2.6

Latest chocolatey package is available here: <https://chocolatey.org/packages/stubby/0.2.6.0>

Latest msi and zip installers:

Description	File	SHA256 Checksum
64bit Windows Installer	stubby-0.2.6.0-x64.msi	c9187906c6cfa294a0673df72cee4e2febb901c4612e026b222d4c9366b2af0f
32bit Windows Installer	stubby-0.2.6.0-x86.msi	2dfbaf9f675fbd2f20cbe6aed44287a95d98a3cdc39fd13ad4c78c17e34452cb
Zip file with 64bit install	stubby-0.2.6.0-x64.zip	e850c58c7b3e16938a9c4b332d779210653d2bf890a7545c94411210de52c1eb
Zip file with 32bit install	stubby-0.2.6.0-x86.zip	466c335449f522c61cad69c78098f2c6615f97021d4ed7326baaac4bfd2ddc72

These contain the following files by the installer.

 The 0.2.5.0 release now provides a 32bit install as well as a 64bit install. On a 64bit Windows installation, a 32bit install will place files in C:\Program Files (x86)\Stubby. All other installs place files in C:\Program Files\Stubby.

- *README.txt* - containing these instructions
- *stubby.exe* - binary
- *stubby.yml* - configuration file
- *getdns_query.exe* - tool for testing stubby
- *getdns_server_mon.exe* - tool for probing servers
- Powershell scripts for modifying system resolvers:
 - *stubby_setdns_windows.ps1*
 - *stubby_resetdns_windows.ps1*
 - Windows 7 versions of Powershell scripts (see below)
 - *stubby_setdns_windows7.ps1*
 - *stubby_resetdns_windows7.ps1*
- Scripts to enable Stubby to be configured as a Scheduled Task
 - *stubby.xml*
 - *stubby.bat*

Configuration

It is recommended to use the default configuration file provided which will use 'Strict' privacy mode and spread the DNS queries among several of the current DNS Privacy test servers. Note that this file contains both IPv4 and IPv6 addresses. It is installed in "*C:\Program Files\Stubby\stubby.yml*"

More information on how to customise the configuration [can be found here](#).

Run Stubby

Simply invoke Stubby on the command line from a command prompt window (To get a command prompt go to the Windows search box and type 'cmd' and then choose the 'Command prompt' option)

```
> "C:\Program Files\Stubby\stubby.exe" -l
```

The *-l* flag enables full logging. Alternatively a specific logging level can be controlled by using the *-v* flag (run "*C:\Program Files\Stubby\stubby.exe -h*" for details of available levels).

 We are working on support for running Stubby as a service on Windows 10. Instructions for setting up a Scheduled task are below.


Test Stubby

A quick test can be done by opening a separate Command prompt window and using *getdns_query* (or your favourite DNS tool) on the loopback address:

```
> "C:\Program Files\Stubby\getdns_query" -s @127.0.0.1 www.example.com
```

You should see a *status* of GETDNS_RESPSTATUS_GOOD and a *rcode* of GETDNS_RCODE_NOERROR in the *getdns_query* output. You should also see a connection being made in the stubby logs.

Modify your upstream resolvers

 Once this change is made all your DNS queries will be re-directed to Stubby and sent over TLS! (You may need to restart some applications to have them pick up the network settings).

For Stubby to re-send outgoing DNS queries over TLS the recursive resolvers configured on your machine must be changed to send all the local queries to the loopback interface on which Stubby is listening.

In most cases your system will use the 'default' DNS servers that are provided by whatever network you are on at the time. Using the two Powershell commands will be all you need to switch back and forth from Stubby to the default DNS settings for the network you are on. (The scripts don't store any DNS config information because it can change dynamically). If you want to double check what servers you are using right now you can use then follow [the instructions below](#) to inspect your system settings. If you have reason to think your system uses specific servers on all networks it might be useful to note your existing default nameservers before making this change so you can use the same instructions to reset them!

To set your nameservers to use Stubby

- From Windows search box type 'cmd' and on the 'Command prompt' option that appears right click and select 'run as Administrator'
- In the command prompt window that appears type

```
PowerShell -ExecutionPolicy bypass -file "C:\Program Files\Stubby\stubby_setdns_windows.ps1"
```

to switch the system DNS resolvers to use Stubby.

You can monitor the DNS traffic using Wireshark watching on port 853.


If you encounter problems or want to turn Stubby off for any reason then reverse this change to restore the default network settings (no DNS Privacy) by running

```
PowerShell -ExecutionPolicy bypass -file "C:\Program Files\Stubby\stubby_resetdns_windows.ps1"
```

Modify your upstream resolvers (Windows 7)

Follow the procedure above, but use the scripts:

- C:\Program Files\Stubby\stubby_setdns_windows7.ps1 and
- C:\Program Files\Stubby\stubby_resetdns_windows7.ps1

 **WARNING:** These scripts can only update DNS servers on the IPv4 service. IPv6 will still use the default DNS servers, sending queries in clear text so one option is to disable IPv6, the other is to manually update the IPv6 addresses (see below).

Create a Scheduled Task

If you want Stubby to always start when you boot your system, you can create a Scheduled task for this. A template for the task is provided.

To create the task just run

```
schtasks /create /tn Stubby /XML "C:\Program Files\Stubby\stubby.xml" /RU <you_user_name>
```

Known Issues

- We are aware of occasional issues when Windows sleeps and resumes when stubby must be restarted to work correctly.
- If you get an error when trying to run Stubby that includes the words "Could not bind on given address" then retry the command from an 'Administrator' Command prompt window
- The '-h' output of stubby.exe shows the wrong path for the installed configuration file. [An issue has been opened for this.](#)


- The installer currently overwrites the stubby.yml file so if changes have been made a backup should be created before upgrading

Manual update of system revolvers on Windows

If you need to manually inspect or change your system revolvers on Windows through the GUI then do the following:

1. Open the Control Panel
2. Choose 'Network and Internet'
3. Choose 'View network status and tasks' under 'Network and Sharing Center'
4. Choose 'Change adapter settings' from the left hand menu
5. Then choose your interface - most likely either 'Wi-fi' or 'Ethernet'
6. In the dialog that appears, click on the 'Properties' button at the bottom
7. In the list that appears double click on 'Internet Protocol Version 4 (TCP/IPv4)'
 - a. You can toggle your DNS between using the default DNS servers provided by the network you are on and setting specific servers using the bottom radio buttons on this page
 - b. Be sure to press OK and then Close to apply the settings.
8. Repeat step 7 for 'Internet Protocol Version 6 (TCP/IPv6)' if you have IPv6 enabled

A helpful screenshot (in German):



Opportunistic mode

If you have changed the default config in the stubby.yml file and are running in Opportunistic mode then you may want to add an alternative DNS server in here for robustness. However DNS queries sent to this server will be sent clear text over UDP/TCP, so this is NOT recommended for Strict mode unless required for bootstrapping (e.g. in a corporate network).